

## HOWTO: License an EXE for Deployment

In order to deploy an application using DotImage, DotAnnotate or DotTwain, the .exe file must be licensed correctly. The following steps outline this procedure. (Note: DotImage OCR requires a runtime license agreement)

If you have only used an Atalasoftware toolkit in a DLL, and are referencing that DLL in an EXE, you must follow these steps on the Executable project, NOT the DLL project. This is because our license can only be embedded into an EXE. Visual Studio will not embed a license if it thinks the license is not used in the code for the EXE. To get around this issue, follow these steps:

1. Add all the Atalasoftware references from your DLL project to the EXE project
  2. (c) Now you are ready to follow the steps below
- 
1. Locate the '[licenses.licx](#)' file. It should be located in the Properties directory (next to AssemblyInfo.cs) inside visual studio project folder (For VB it would live in the MyProject folder next to AssemblyInfo.vb). If this file does not exist, create it. (Note: For a console application, you must include this file in the project so it shows up in the solution explorer, otherwise visual studio will ignore it. Likewise, if you had to manually create the file for any reason, be sure to click "show all files" in the solution explorer, find your licenses.licx file, and right-click to select the option to include the file in your project.)
  2. Examine the references that are in your project. For each Atalasoftware reference, refer to the table below and add the corresponding line to the .licx file. Keep in mind that a few references are licensed by the same license file, and therefore they have the exact same entry in the .licx file. If the entry was already entered, there is no need to add it again. (Note: If an entry in the licx was automatically generated by the visual studio designer, it may contain version information. You should delete all extra information other than what is listed below. This version information may cause problems when you upgrade you DotImage SDK.)
  3. Compile your application (using a \*REbuild\*) to embed the licenses as a resource in the .exe file. Visual studio will automatically find the .licx file and embed the correct licenses into your application. No special steps need to be taken at this point

To License this Assembly ...	Add This Line
Atalasoftware.DotAnnotate	Atalasoftware.Annotate.UI.AnnotateViewer, Atalasoftware.DotImage.Annotate

## HOWTO: License an EXE for Deployment

Atalasoftware.DotAnnotate.Ink	Atalasoftware.Annotate.UI.AnnotateViewer, Atalasoftware.DotImage.Annotate
Atalasoftware.DotImage.Annotate	Atalasoftware.Annotate.UI.AnnotateViewer, Atalasoftware.DotImage.Annotate
Atalasoftware.dotImage.BarcodeReader	Atalasoftware.Barcoding.BarReader, Atalasoftware.dotImage.BarcodeReader
Atalasoftware.dotImage.Barcoding	Atalasoftware.Barcoding.BarCodeReader, Atalasoftware.dotImage.Barcoding
Atalasoftware.dotImage.Barcoding.Reading	Atalasoftware.Barcoding.Reading.BarCodeReader, Atalasoftware.dotImage.Barcoding.Reading
Atalasoftware.dotImage.Barcoding.Writing	Atalasoftware.Barcoding.Writing.BarcodeWriter, Atalasoftware.dotImage.Barcoding.Writing
Atalasoftware.dotImage	Atalasoftware.Imaging.AtalaImage, Atalasoftware.dotImage
Atalasoftware.dotImage.Dwg	Atalasoftware.Imaging.Codec.CadCam.DwgDecoder, Atalasoftware.dotImage.Dwg
Atalasoftware.dotImage.Dicom	Atalasoftware.Imaging.Codec.Dicom.DicomDecoder, Atalasoftware.dotImage.Dicom
Atalasoftware.dotImage.FormsProcessing	Atalasoftware.FormsProcessing.Omr.OmrEngine, Atalasoftware.dotImage.FormsProcessing
Atalasoftware.dotImage.IntelJpeg	Atalasoftware.Imaging.AtalaImage, Atalasoftware.dotImage
Atalasoftware.dotImage.Isis	Atalasoftware.Isis.IsisAcquisition,

## HOWTO: License an EXE for Deployment

	Atalasoftware.Imaging.Isis
Atalasoftware.Imaging.Jbig2	Atalasoftware.Imaging.Codec.Jbig2.Jb2Decoder, Atalasoftware.Imaging.Jbig2
Atalasoftware.Imaging.Jpeg2000	Atalasoftware.Imaging.Codec.Jpeg2000.Jp2Decoder, Atalasoftware.Imaging.Jpeg2000
Atalasoftware.Imaging.Lib	Atalasoftware.Imaging.AtalaImage, Atalasoftware.Imaging
Atalasoftware.Ocr	Atalasoftware.Ocr.TranslatorCollection, Atalasoftware.Ocr
Atalasoftware.Ocr.Abbby	Atalasoftware.Ocr.TranslatorCollection, Atalasoftware.Ocr
Atalasoftware.Ocr.GlyphReader	Atalasoftware.Ocr.TranslatorCollection, Atalasoftware.Ocr
Atalasoftware.Ocr.RecoStar	Atalasoftware.Ocr.TranslatorCollection, Atalasoftware.Ocr
Atalasoftware.Ocr.Tesseract	Atalasoftware.Ocr.TranslatorCollection, Atalasoftware.Ocr
Atalasoftware.Ocr.Tesseract3	Atalasoftware.Ocr.TranslatorCollection, Atalasoftware.Ocr
<p><b>* Atalasoftware.Imaging.Office *</b></p> <p><b>Both OfficeAdapterDecoeer and OfficeDecoder "live in" the Office Assembly. *</b></p>	<p>If using OfficeAdapterDecoder (10.6): Atalasoftware.Imaging.Codec.Office.OfficeAdapterDecoder, Atalasoftware.Imaging.Office</p> <p>If using OfficeDecoder (10.7 and newer only) Atalasoftware.Imaging.Codec.Office.OfficeDecoder,</p>

## HOWTO: License an EXE for Deployment

	Atalasoftware.dotImage.Office
Atalasoftware.dotImage.Pdf	Atalasoftware.Imaging.AtalaImage, Atalasoftware.dotImage
<b>* Atalasoftware.dotImage.PdfDoc *</b> <b>ONLY if using PdfGeneration / DotPdf</b>	Atalasoftware.PdfDoc.Generating.PdfGeneratedDocument, Atalasoftware.PdfDoc
<b>* Atalasoftware.dotImage.PdfDoc *</b> <b>If using PdfDocument, but not PdfGeneration</b>	Atalasoftware.PdfDoc.PdfDocument, Atalasoftware.PdfDoc
Atalasoftware.dotImage.PdfRasterizer	Atalasoftware.Imaging.Codec.Pdf.PdfDecoder, Atalasoftware.dotImage.PdfRasterizer
Atalasoftware.dotImage.PdfReader <i>(up through 10.7)</i>  Atalasoftware.dotImage.PdfReader <i>(11.0 and newer)</i>	Atalasoftware.Imaging.Codec.Pdf.PdfDecoder, Atalasoftware.dotImage.PdfReader  Atalasoftware.Imaging.Codec.Pdf.PdfDecoder, Atalasoftware.dotImage.PdfReader
Atalasoftware.dotImage.Raw	Atalasoftware.Imaging.AtalaImage, Atalasoftware.dotImage
Atalasoftware.dotImage.WebControls	Atalasoftware.Imaging.AtalaImage, Atalasoftware.dotImage
Atalasoftware.dotImage.WinControls	Atalasoftware.Imaging.WinControls.WorkspaceViewer, Atalasoftware.dotImage.WinControls
<b>* Atalasoftware.dotImage.Word *</b> <b>Word assembly replaced with Office assembly in 10.6</b>	Atalasoftware.Imaging.Codec.Word.WordDecoder, Atalasoftware.dotImage.Word

## HOWTO: License an EXE for Deployment

Atalasoftware.dotImage.Wpf	Atalasoftware.Imaging.Wpf.AtalaImageViewer, Atalasoftware.dotImage.Wpf
Atalasoftware.dotTwain	Atalasoftware.Twain.Acquisition, Atalasoftware.DotTwain

**If you are using DotImage 4.0 or Previous then please use the below lines for DotAnnotate, DotAnnotate.Ink, or DotImage.DotAnnotate**

**Atalasoftware.DotAnnotate Atalasoftware.Imaging.Annotate.AnnotateViewer,  
Atalasoftware.DotImage.Annotate**

**Atalasoftware.DotAnnotate.Ink Atalasoftware.Imaging.Annotate.AnnotateViewer,  
Atalasoftware.DotImage.Annotate**

**Atalasoftware.DotImage.Annotate Atalasoftware.Imaging.Annotate.AnnotateViewer,  
Atalasoftware.DotImage.Annotate**

4. Test your application. To emulate a client machine you can simply relocate your development licenses so that DotImage cannot find them. The license file are located at "C:\Documents and Settings\Local Settings\Application Data\Atalasoftware\DotImage X.0" (XP) or "C:\Users\AppData\Local\Atalasoftware\DotImage X.0". Create a temporary folder and move all of the .lic file there. Make sure to relocate any license files for other versions of DotImage also. Now run your exe. When it starts, DotImage should read the licenses that were embedded into the exe, so if the application runs without a license error you know that the licenses were embedded successfully.
5. Fix problems. If you have any license problems, please see one of the related articles.

Original Article:

Q10128 - HOWTO: License an EXE for Deployment

Atalasoftware Knowledge Base

<http://www.atalasoftware.com/KB2/KB/50311/HOWTO-License-an-EXE-for-Deployment>